

SPECIFICATION
---------------

**DLL Specification** 

CRT-310N
2015/09/01
V1.0
1/26

## **CRT-310N DLL Specification**

Copyright: CREATOR (CHINA) TECH CO., LTD

Website: www.china-creator.com E-Mail: hbhcb@china-creator.com

Tel: 0755-26710345 26710456

Document Version: V1.0 Date: 2010-02-26

#### **WINDOWS DLL Specification:**

Our company provides DLL for Windows32 and include following files:

1. CRT\_310NV3.H 32 digit DLL header file

CRT\_310NV3.LIB32 digit input libraries

3. CRT\_310NV3.DLL WINDOWS 32 digit libraries

#### CRT-310N (V1.0) Support card type:

1. RFID Card: ISO/IEC 14443 TYPE A / B, MIFARE one (S50, S70, UL)

2. IC Card:

SLE4428, SLE4442

24C01A, 24C02, 24C04, 24C08, 24C16, 24C32, 24C64

Contact CPU Card (T=0/T=1)

SAM/SIM Card (T=0/T=1)

Magnetic Card

#### Notes:

- 1. Code examples of DLL running on VC6, VB6, DELPHI7, C++BUILD6, PB9, VB2005.NET, V#2005.NET environment are provided.
- 2. Technical support for DLL running on Linux/Unix (.so) can be provided for a large demand.
- 3. Technical support for JAVA environment can be provided for a large demand.
- 4. Technical support for OCX design and Web invocation can be provided for a large demand.
- 5. For optimal work effectiveness, we recommend you to use power-supply which is 24V and more than 2A(Above 2.5A for Hi-Co)



# Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 2/26

## **DLL Specification**

## **Contents**

1. API Specification (RS	232 Mode)	3
1.1 Open Com function	(Default baud rate38400bps)	3
1.2 Open Com Port by	Specified baud rate	4
1.3 Close Com Port Fur	nction	5
1.4 Command Function		6
1.5 IC Card Transporta	tion Command	6
1.5 IC Card Transporta	tion Command	7
1.6 Cancel Command F	unction	8
2 API Specification (USB N	lode)	9
2.1 Open USB Function		9
2.1 Close USB Function		10
2.3 Command Function		11
2.4 IC Card Transporta	tion Comman	11
2.4 IC Card Transporta	tion Comman	12
3 Code Example		13
	ole	
3.2 Call Function Speci	fication	13
3.3 Code Example 1	(Magnetic card operation)	14
3.4 Code Example 2 (	CPU Card Operation)	21



<b>SPEC</b>		$\Gamma \wedge \Lambda T$	$\square$
SPEU	IF	ICAL	ION

## **DLL Specification**

Model No.	CRT-310N
Date	2015/09/01
Ver.	V1.0
Page	3/26

## 1. API Specification (RS232 Mode)

#### 1.1 Open Com function (Default baud rate38400bps)

HANDLE APIENTRY CRT310NROpen (char \*Port)

#### Parameter:

Port: Serial Number String


E.g.: CRT310NROpen("COM1")

#### **Return:**

0 (Com open error)

Possible reason:

- 1 Invalid Serial Number String
- 2 The com occupies by other device
- <>0 Com Open Success



#### Notes:

- 1) Call this function before others.
- 2) Enable to open several com ports to get serial number string, but disable to open one port twice at same time.
- 3) Close com port by using CRT310NRClose() after the completion of all operations.



## Ver. Page

Model No.

CRT-310N 2015/09/01 V1.0

4/26

### **DLL Specification**

#### 1.2 Open Com Port by Specified baud rate

HANDLE APIENTRY CRT310NROpenWithBaut (char \*Port, unsigned int Baud rate);

#### Parameter:

Port: Serial port string Baud rate: Baud rate

Baud rate=9600, 19200, 38400, 57600, 115200<sub>o</sub>


Eg: CRT310NROpenWithBaut ("COM1", 38400)

#### Return:

0 (Com open error)

Possible reason:

- 1 Invalid Serial Number String
- 2 The com occupies by other device



#### Notes:

- 1) Call this function before others.
- 2) Enable to open several com ports to get serial number string, but disable to open one port twice at same time.
- 3) Close comport by using CRT310NRClose() after the completion of all operations.



## n Date Ver. Page

Model No.

#### CRT-310N 2015/09/01 V1.0

5/26

**DLL Specification** 

#### 1.3 Close Com Port Function


int APIENTRY CRT310NRClose (HANDLE ComHandle)

Patameter:

ComHandle: Com Handle

Return:

=0 Success <>0 Fail



Notes: Combined application with CRT310NROpen () or CRT310NRopenWithBaut function, Close com port after usage of com port.



## **DLL Specification**

Model No.	CRT-310N
Date	2015/09/01
Ver.	V1.0
Page	6/26

#### 1.4 Command Function

int APIENTRY RS232\_ExeCommand (HANDLE ComHandle, BYTE TxCmCode, BYTETxPmCode, int TxDataLen, BYTE TxData, BYTE \*RxReplyType, BYTE \*RxStCode1,BYTE \*RxStCode0, int \*RxDataLen, BYTE RxData);

Function:

Execute command and return the result

Parameter:

ComHandle: Com handle TxCmCode: Command Code TxPmCode: Parameter Code

TxDataLen: Extra command data length TxData: Extra command data package

RxReplyType: Reply Type

0x50: Execute successful

0x4E: Execute fail

0x10: Communication is cancel by slave (NAK)

0x20: Communication failure

0x30: Command is cancel by HOST (DLE, EOT)

RxStCode1: Return State code 1 // Pls see more detain from Status code and error code of communication protocol

RxStCode0: Return State code 0 //Pls see more detain from Status code and error code of communication protocol

RxDataLen: Return Package length

RxData: Return package data

#### Return:


=0 Successful

<>0 Fail


2.

Parameter example base on communication protocol

1. (Send command format)



(Receive command format)





## \_\_\_\_

Page

## Model No. CRT-310N Date 2015/09/01 Ver. V1.0

7/26

#### **DLL Specification**

#### 1.5 IC Card Transportation Command

int APIENTRY RS232\_ICCardTransmit (HANDLE ComHandle, BYTE TxCmCode, BYTE TxPmCode, int TxDataLen, BYTE TxData, BYTE \*RxReplyType, BYTE \*RxStCode1,BYTE \*RxStCode0, BYTE \*RxCmCode, BYTE \*RxPmCode, int \*RxDataLen, BYTE RxData)

#### Function:

Execute command and return

Notes: Comparing to command function (  $RS232\_ExeCommand$  ), it add two parameters(RxCmCode and RxPmCode)

#### Parameters:

Parameter:

ComHandle: Com handle TxCmCode: Command Code TxPmCode: Parameter Code

TxDataLen: Extra command data length TxData: Extra command data package

RxReplyType: Reply Type

0x50: Execute successful

0x4E: Execute fail

0x10: Communication is cancel by slave (NAK)

0x20: Communication failure

0x30: Command is cancel by HOST (DLE, EOT)

RxStCode1: Return State code 1 // Please see more detain from Status code and error code of communication protocol

RxStCode0: Return State code 0 //Please see more detain from Status code and error code of communication protocol

RxDataLen: Return Package length RxData: Return package data


#### Return:

=0 Successful

<>0 Fail

Parameter example base on communication protocol

1 (Send command format)



TxDataLen=0x05  $TxData=\{0x00,0x84,0x00,0x00,0x08\}$ 

2 (Receive command format) RxCmCode=0x34

F2 00 0F 50 49 34 30 32 21 A8 04 63 D6 FE 3D 95 90 00 31 50

RxReplyType=0x50 \\
RxStCode1=0x30 RxStCode0=0x32



<b>SPECI</b>	$\Gamma \cap \Lambda$	$\Box$	١
SPEU	IUAI		N

## **DLL Specification**

Model No.	CRT-310N
Date	2015/09/01
Ver.	V1.0
Page	8/26

#### 1.6 Cancel Command Function


int APIENTRY CancelCommand (HANDLE ComHandle);

Function:

Cancel recent operation, finish following operation

- ① Send "DLE,EOT" control code to slave and waiting for "DLE,EOT"
- ② Cancel the command. For example, card-in command, it can be cancel when the card is inserting by this command.

Parameter:





#### **DLL Specification**

Model No.	CRT-310N
Date	2015/09/01
Ver.	V1.0
Page	9/26

## 2 API Specification (USB Mode)

#### 2.1 Open USB Function

HANDLE APIENTRY CRT310NUOpen ();

Parameter:


Eg: CRT310NUopen();

Return:

0 Com open fail

Possible Reason:

- ① Equipment is not connected, please check the power and communication cable
- 2 Power is not compromised, Please check if the power supply is 24V and above 2A(Write Hi-co need 2.5A)



#### Notes:

- 1) Call this function before others.
- 2) Enable to open several com ports to get serial number string, but disable to open one port twice at same time.
- 3) Close com port by using CRT310NUClose() after the completion of all operations.



SPEC		$\Gamma \cap \Lambda$	
SPEU	, I F	IUAI	

## **DLL Specification**

Model No.	CRT-310N
Date	2015/09/01
Ver.	V1.0
Page	10/26

#### 2.1 Close USB Function

int APIENTRY CRT310NUClose (HANDLE ComHandle)

Parameter:


ComHandle: Com Handle

Return:

=0 Success

<>0 Fail

Notes: Combine with CRT310NUOpen () function and use this command to close the equipment after operation.





## \_\_\_\_

## Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 11/26

**DLL Specification** 

#### 2.3 Command Function

int APIENTRY USB\_ExeCommand (HANDLE ComHandle, BYTE TxCmCode, BYTE TxPmCode, int TxDataLen, BYTE TxData, BYTE \*RxReplyType, BYTE \*RxStCode1, BYTE \*RxStCode0, int \*RxDataLen, BYTE RxData) Function:

Execute command and return

Parameter:

ComHandle: Com handle TxCmCode: Command Code TxPmCode: Parameter code

TxDataLen: Extra Command data length TxData: Extra Command data package

RxReplyType: Reply Type 0x50 : Successful 0x4E : Fail

RxStCode1: Return Code 1 // Please see more detain from Status code and error code of communication protocol

RxStCode0: Return Code 0 // Please see more detain from Status code and error code of communication protocol

RxDataLen: Return package length


RxData: Return Data

#### Return:

=0 Success


<>0 Fail (Close USB communication automatically, need to rerun CRT310NUopen to connect equipment) Parameter example is shown as below:

#### 1. (Send command format)



TxDataLen=0x05  $TxData=\{0x00,0x84,0x00,0x00,0x08\}$ 

#### (Receive command format)





## DLL Specification

Model No.	CRT-310N
Date	2015/09/01
Ver.	V1.0
Page	12/26

#### 2.4 IC Card Transportation Comman

int APIENTRY USB\_ICCardTransmit (HANDLE ComHandle, BYTE TxCmCode, BYTE TxPmCode, int TxDataLen, BYTE TxData, BYTE \*RxReplyType, BYTE \*RxStCode1,BYTE \*RxStCode0, BYTE \*RxCmCode, BYTE \*RxPmCode, int \*RxDataLen, BYTE RxData);

Function:

Execute command and return

Notes: Comparing to (USB\_ExeCommand) it add two parameters (RxCmCode and RxPmCode)

Parameter:

ComHandle: Com handle TxCmCode: Command Code TxPmCode: Parameter code

TxDataLen: Extra Command data length TxData: Extra Command data package

RxReplyType: Reply Type 0x50 : Successful 0x4E : Fail

RxStCode1: Return Code 1 // Please see more detain from Status code and error code of communication protocol

RxStCode0: Return Code 0 // Please see more detain from Status code and error code of communication protocol

RxDataLen: Return package length

RxData: Return Data

Return:


=0 Success

<>0 Fail (Close USB communication automatically, need to rerun CRT310NUopen to connect equipment) Parameter example is shown as below:

#### 1. (Send command format)



#### (Receive command format)





$\mathbf{C}$		$\sim$ 1		$\sim \Lambda$	$\Gamma I \cap I$	N١
OI	ΓE.	U	F	CA	HUI	V

## **DLL Specification**

Model No.	CRT-310N
Date	2015/09/01
Ver.	V1.0
Page	13/26

### 3 Code Example

#### 3.1 Call Function Specification


USB interface is as the same as RS232

- 1. Equipment Connection
- ( USB interface call CRT310NUopen function and RS232 interface call CRT310NRopen function )
- 2. Communication Procedure

USB interface call USB\_ExeCommand function and RS232 interface call RS232\_ExeCommand function. USB will close the communication if function call is failure, and need to rerun CRT310NUopen RS232will not close the communication if function call is failure

3、Close Com Port

( USB interface call CRT310NUClose function and RS232 interface call CRT310NRClose function )





## Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 14/26

#### **DLL Specification**

#### 3.2 Code Example 1 (Magnetic card operation)

```
HANDLE hCom;
                        // Target device's HANDLE
    int rc=0;
                         //Result
    unsigned char CmCode;
    unsigned char PmCode;
    int CmDataLen;
    unsigned char CmData[1024];
    unsigned char ReType;
    unsigned char St1;
    unsigned char St0;
    int ReDataLen;
    unsigned char ReData[1024];
// Open Comm. port
    hCom=CRT310NROpenWithBaut ("COM1",38400);
    if(hCom <= 0)
         // failed
    }
    else
        // successfully.
}
// Initialize
{
    memset(CmData,0x00,sizeof(CmData));
    CmCode=0x30; // Initialize command
    PmCode=0x36; // Parameter code
    CmDataLen=11; // Data size (bytes)
    CmData[0]=0x33;
    CmData[1]=0x32;
    CmData[2]=0x34;
    CmData[3]=0x30;
    CmData[4]=0x30;// fm Not use. Always 30H
    CmData[5]=0x33;// Pd
    CmData[6]=0x30;// Wv
    CmData[7]=0x30;// Sh
    CmData[8]=0x31;// Ds
```



}

{

#### **SPECIFICATION**

#### Model No. **CRT-310N** 2015/09/01 Date Ver. V1.0 15/26 Page

```
CmData[9]=0x30;// Ty
    CmData[10]=0x31;// Cp
    rc=RS232\_ExeCommand(hCom,CmCode,PmCode,CmDataLen,CmData,
                          &ReType,&St1,&St0,&ReDataLen,ReData);
    if(rc==0)
         // Initialize command successfully finished.
         if (ReType==0x50)
             // Received positive reply
         else (ReType==0x4e)
           // Received negative reply
    else
         //Communication Error
           // Initialize command failed.
// Setting Card In by Mag card
    memset(CmData,0x00,sizeof(CmData));
    CmCode= 0x3a; // Card In
    PmCode=0x32; // by Mag card
    CmDataLen=0; // Data size
    rc=RS232_ExeCommand(hCom,CmCode,PmCode,CmDataLen,CmData,
                           &ReType,&St1,&St0,&ReDataLen,ReData);
    if(rc!=0) || ReType != 0x50)
         // Command sending failed or command execution failed
             ResErrMsg(St1,St0);
                                    // ResErrMsg is a function to show the reason of error
  // Details please see from error code of communication protocol
// Request Status
    memset(CmData,0x00,sizeof(CmData));
    CmCode= 0x31; // Status request command
```



## Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 16/26

```
PmCode= 0x30; // Parameter code
                           CmDataLen=0; // Data size
                           rc=RS232\_ExeCommand (hCom, CmCode, PmCode, CmDataLen, CmData, CmDataLen, CmDataLen
                                                                                                                                                                        &ReType,&St1,&St0,&ReDataLen,ReData);
                           if(rc==0)
                                                        if (ReType==0x50)
                                                                                   //Execute Ok
                                                                                                  if(St1 == '0' \&\& St1 == '2')
                                                                                                                             // status code="02"
                                                                                                                             // Detected a card inside of Card Reader/Writer
                                                         else (ReType==0x4e)
                                                                                   //Command execution failed
                                                                                   ResErrMsg(St1,St0);
                           else
                                                                                                                //Communication Error
// Read Track 1 of Mag card's tracks
                           memset(CmData,0x00,sizeof(CmData));
                           CmCode= 0x36; // Read Mag Card
                           PmCode=0x31; // Track 1
                           CmDataLen=0; // Data size
                           rc=RS232\_ExeCommand(hCom,CmCode,PmCode,CmDataLen,CmData,Robert Compart Code,CmDataLen,CmData,Robert Code,CmData,Robert Co
                                                                                                                                                                        &ReType,&St1,&St0,&ReDataLen,ReData);
                           if(rc==0)
                                                        if (ReType==0x50)
                                                         {
                                                                                   //Read track data OK
                                                                                   if (ReData[0]==0x50)
                                                                                                                CString Tra1Buf,t;
                                                                                                                int n;
                                                                                                                for(n=1; n<ReDataLen; n++)</pre>
```



else

}

{

{

### **SPECIFICATION**

#### Model No. **CRT-310N** 2015/09/01 Date Ver. V1.0 17/26 Page

```
t.Format("%c",ReData[n]);
                           Tra1Buf += t;
                           t="";
                  //Tra1Buf is the buffer of track 1 data
              }
             else if (ReData[0]==0x4e)
                  //Read track data Error
                  switch(ReData[2])
                       case 36:
                                  //No start bits (STX)
                           break;
                                  //No stop bits (ETX)
                       case 37
                           break;
                       case 30:
                                  //Byte Parity Error(Parity))
                           break;
                       case 38:
                                   //Parity Bit Error(LRC)
                           break;
                       case 34:
                                   //Card Track Data is Blank
                       case 33:
                                    //Only(SS-ES-LRC)
                           break;
         else (ReType==0x4e)
             // Command execution failed
             ResErrMsg(St1,St0);
         //Communication Error
// Read Track 2 of Mag card's tracks
    memset(CmData,0x00,sizeof(CmData));
    CmCode= 0x36; // Read Mag Card
    PmCode=0x32; // Track 2
    CmDataLen=0; // Data size
    rc=RS232_ExeCommand(hCom,CmCode,PmCode,CmDataLen,CmData,
                           &ReType,&St1,&St0,&ReDataLen,ReData);
```



# Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 18/26

```
if(rc==0)
    if (ReType==0x50)
         //Read track data OK
         if (ReData[0]==0x50)
              CString Tra1Buf,t;
              int n;
              for(n=1; n<ReDataLen; n++)</pre>
                        t.Format("%c",ReData[n]);
                        Tra1Buf += t;
                        t="";
              //Tra1Buf is the buffer of track 2 data
         else if (ReData[0]==0x4e)
              //Read track data Error
              switch(ReData[2])
                   case 36:
                               //No start bits (STX)
                        break;
                   case 37
                               //No stop bits (ETX)
                        break;
                   case 30:
                               //Byte Parity Error(Parity))
                        break;
                   case 38:
                                //Parity Bit Error(LRC)
                        break;
                   case 34:
                                //Card Track Data is Blank
                   case 33:
                                //Only(SS-ES-LRC)
                        break;
              }
    else (ReType==0x4e)
         // Command execution failed
         ResErrMsg(St1,St0);
else
    //Communication Error
```



## Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 19/26

```
}
// Read Track 3 of Mag card's tracks
                memset(CmData,0x00,sizeof(CmData));
                CmCode= 0x36; // Read Mag Card
                PmCode=0x33; // Track 3
                CmDataLen=0; // Data size
                rc=RS232\_ExeCommand (hCom, CmCode, PmCode, CmDataLen, CmData, CmDataLen, CmDataLen
                                                                                                    &ReType,&St1,&St0,&ReDataLen,ReData);
                if(rc==0)
                                 if (ReType==0x50)
                                                 //Read track data OK
                                                  if (ReData[0]==0x50)
                                                                  CString Tra1Buf,t;
                                                                  int n;
                                                                  for(n=1; n<ReDataLen; n++)</pre>
                                                                                                    t.Format("%c",ReData[n]);
                                                                                                    Tra1Buf += t;
                                                                                                    t="";
                                                                  //Tra1Buf is the buffer of track 3 data
                                                  else if (ReData[0]==0x4e)
                                                                  //Read track data Error
                                                                  switch(ReData[2])
                                                                                   case 36:
                                                                                                                            //No start bits (STX)
                                                                                                   break;
                                                                                  case 37
                                                                                                                            //No stop bits (ETX)
                                                                                                    break;
                                                                                  case 30:
                                                                                                                            //Byte Parity Error(Parity))
                                                                                                   break;
                                                                                  case 38:
                                                                                                                                //Parity Bit Error(LRC)
                                                                                                    break;
                                                                                  case 34:
                                                                                                                                //Card Track Data is Blank
                                                                                   case 33:
                                                                                                                                //Only(SS-ES-LRC)
                                                                                                   break;
                                                                  }
                                 }
```



# Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 20/26

```
else (ReType==0x4e)
             // Command execution failed
             ResErrMsg(St1,St0);
         }
    else
         //Communication Error
}
// Closes communications between the Host Computer and the Card Reader/Writer
CRT310NRClose (hCom);
```



## Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 21/26

## **DLL Specification**

#### 3.4 Code Example 2 (CPU Card Operation)

```
// Target device's HANDLE
    HANDLE hCom;
    int rc=0;
                         //Result
    unsigned char CmCode;
    unsigned char PmCode;
    int CmDataLen;
    unsigned char CmData[1024];
    unsigned char ReType;
    unsigned char St1;
    unsigned char St0;
    int ReDataLen;
    unsigned char ReData[1024];
 Open Comm. port
    hCom= CRT310NROpenWithBaut ("COM1",38400);
    if(hCom <= 0)
         // failed
    else
        // successfully.
}
// Initialize
{
    memset(CmData,0x00,sizeof(CmData));
    CmCode=0x30; // Initialize command
    PmCode=0x30; // Parameter code
    CmDataLen=11; // Data size (bytes)
    CmData[0]=0x33;
    CmData[1]=0x32;
    CmData[2]=0x34;
    CmData[3]=0x30;
    CmData[4]=0x30;// fm Not use. Always 30H
    CmData[5]=0x33;// Pd
    CmData[6]=0x30;// Wv
    CmData[7]=0x30;// Sh
    CmData[8]=0x31;// Ds
    CmData[9]=0x30;// Ty
```



## Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 22/26

```
CmData[10]=0x31;// Cp
             rc=RS232\_ExeCommand (hCom, CmCode, PmCode, CmDataLen, CmData, CmDataLen, CmD
                                                                                         &ReType,&St1,&St0,&ReDataLen,ReData);
             if(rc==0)
                             // Initialize command successfully finished.
                              if (ReType==0x50)
                                             // Received positive reply
                              else (ReType==0x4e)
                                             // Received negative reply
             else
                                             //Communication Error
                                            // Initialize command failed.
// Setting Card In by Switch
             memset(CmData,0x00,sizeof(CmData));
             CmCode= 0x3a; // Card In
             PmCode=0x30; // by Switch
             CmDataLen=0; // Data size
             rc=RS232_ExeCommand(hCom,CmCode,PmCode,CmDataLen,CmData,
                                                                                             &ReType,&St1,&St0,&ReDataLen,ReData);
             if(rc==0)
              {
                              // Command successfully finished.
                              if (ReType==0x50)
                                             // Received positive reply
                              else (ReType==0x4e)
                                     // Received negative reply
                                             ResErrMsg(St1,St0); // ResErrMsg is a function ,please see the error code of communication protocol
                              }
```



## Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 23/26

```
else
                                                     //Communication Error, Command failed.
}
// Request Status
                 memset(CmData,0x00,sizeof(CmData));
                 CmCode= 0x31; // Status request command
                 PmCode= 0x30; // Parameter code
                 CmDataLen=0; // Data size
                 rc = RS232\_ExeCommand (hCom, CmCode, PmCode, CmDataLen, CmData, CmDataLen, CmData, CmDataLen, CmData, CmDataLen, CmData, CmDataLen, CmDataLen, CmData, CmDataLen, CmData, CmDataLen, CmD
                                                                                                           &ReType,&St1,&St0,&ReDataLen,ReData);
                 if(rc==0)
                                   if (ReType==0x50)
                                                    //Execute Ok
                                                              if(St1 == '0' && St1 == '2')
                                                                                // status code="02"
                                                                                // Detected a card inside of Card Reader/Writer
                                   else (ReType==0x4e)
                                                     //Command execution failed
                                                     ResErrMsg(St1,St0);
                 else
                                                                       //Communication Error
                                    }
// Switches IC contact on
                 memset(CmData,0x00,sizeof(CmData));
                 CmCode= 0x40; // IC contact
                 PmCode=0x30; // IC contact set
                 CmDataLen=0; // Data size
```



## Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 24/26

```
rc=RS232\_ExeCommand (hCom, CmCode, PmCode, CmDataLen, CmData, CmDataLen, CmD
                                                                                                                                                          &ReType,&St1,&St0,&ReDataLen,ReData);
                        if(rc!=0) || ReType != 0x50)
                          {
                                                  // Command sending failed or command execution failed
                                                   goto _EXIT1;
}
// Activates CPU card
                        memset(CmData,0x00,sizeof(CmData));
                        CmCode= 0x49; // IC card control
                        PmCode=0x30; // Activate
                        CmDataLen=1; // Data size
                                                                                                           //Choice Mode
                        If (true)
                          {
                                                   CmData[0]=0x30;
                                                                                                                                                                                  //EMV2000 V4.0 Vcc=5v
                        else
                                                   CmData[0]=0x33;
                                                                                                                                                                          // ISO/IEC7816-3
                        rc=RS232\_ExeCommand (hCom, CmCode, PmCode, CmDataLen, CmData, CmDat
                                                                                                                                                          &ReType,&St1,&St0,&ReDataLen,ReData);
                        if(rc!=0))
                          {
                                                   // Command sending failed or command execution failed
                                                   goto _EXIT2;
                          }
                        else
                                                   if (ReType==0x50)
                                                                             CString t;
                                                                            CString TempBuf="";
                                                                             for(int n=1; n<ReDataLen; n++) //
                                                                                                                                                                                                                                                                                     ATR= start from n= 1
                                                                              {
                                                                                                      t.Format("%02x",ReData[n]);
                                                                                                      TempBuf += t;
                                                                                                      t="";
                                                                              }
                                                                            //TempBuf is the buffer of ATR data
                                                   else //(ReType==0x4e)
```



{

### **SPECIFICATION**

# Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 25/26

```
// Command execution failed
             SANKYOErrMsg(St1,St0);
    }
// Exchanges data between the Host Computer and IC card
    memset(CmData,0x00,sizeof(CmData));
    CmCode= 0x49; // IC card control
    PmCode=0x39; // Deactivate
    CmDataLen=5; // Data size
    CmData[0]=0x00;
    CmData[1]=0x84;
    CmData[2]=0x00;
    CmData[3]=0x00;
    CmData[4]=0x08;
    rc=RS232_ExeCommand(hCom,CmCode,PmCode,CmDataLen,CmData,
                          &ReType,&St1,&St0,&ReDataLen,ReData);
    if(rc!=0)
        // ICCardTransmit failed
    else
    {
        if (ReType==0x50)
             CString t;
             CString TempBuf="";
             for(int n=0; n<ReDataLen; n++)
                 t.Format("%02x",ReData[n]);
                 TempBuf += t;
                 t="";
             // TempBuf is the buffer of R-APDU data
        else //(ReType==0x4e)
             // Command execution failed
             SANKYOErrMsg(St1,St0);
    }
```



## Model No. CRT-310N Date 2015/09/01 Ver. V1.0 Page 26/26

```
}
 // Deactivates IC card
                            memset(CmData,0x00,sizeof(CmData));
                            CmCode= 0x49; // IC card control
                            PmCode=0x31; // Deactivate
                            CmDataLen=0; // Data size
                            rc=RS232\_ExeCommand (hCom, CmCode, PmCode, CmDataLen, CmData, CmData, CmDataLen, CmDa
                                                                                                                                                                    &ReType,&St1,&St0,&ReDataLen,ReData);
                            if(rc!=0) || ReType != 0x50)
                                                       // Command sending failed or command execution failed
   _EXIT2:
 // Switches IC contact off
                             memset(CmData,0x00,sizeof(CmData));
                            CmCode= 0x40; // IC contact
                            PmCode=0x32; // IC contact release
                            CmDataLen=0; // Data size
                            rc=RS232\_ExeCommand (hCom, CmCode, PmCode, CmDataLen, CmData, CmDat
                                                                                                                                                                    &ReType,&St1,&St0,&ReDataLen,ReData);
                            if(rc!=0) || ReType != 0x50)
                                                       // Command sending failed or command execution failed
 }
 _EXIT1:
// Closes communications between the Host Computer and the Card Reader/Writer
CRT310NRClose (hCom);
 _EXIT:
```